



libvaxdata: VAX Data Format Conversion Routines

By Lawrence M. Baker

Open-File Report 2005–1424

U.S. Department of the Interior
U.S. Geological Survey

U.S. Department of the Interior
Gale A. Norton, Secretary

U.S. Geological Survey
P. Patrick Leahy, Acting Director

U.S. Geological Survey, Reston, Virginia 2005
Revised and reprinted: 2005

For product and ordering information:
World Wide Web: <http://www.usgs.gov/pubprod>
Telephone: 1-888-ASK-USGS

For more information on the USGS—the Federal source for science about the Earth,
its natural and living resources, natural hazards, and the environment:
World Wide Web: <http://www.usgs.gov>
Telephone: 1-888-ASK-USGS

Suggested citation:
Baker, L.M., 2005, libvaxdata: VAX Data Format Conversion Routines: U.S. Geological Survey Open-File
Report 2005–1424 (<http://pubs.usgs.gov/of/2005/1424/>).

Any use of trade, product, or firm names is for descriptive purposes only and does not imply
endorsement by the U.S. Government.

Although this report is in the public domain, permission must be secured from the individual
copyright owners to reproduce any copyrighted material contained within this report.

Although this program has been used by the USGS, no warranty, expressed or implied, is made by the USGS
or the United States Government as to the accuracy and functioning of the program and related program
material, nor shall the fact of distribution constitute any such warranty, and no responsibility is assumed by
the USGS in connection therewith.

libvaxdata: VAX Data Format Conversion Routines

By Lawrence M. Baker

Introduction

libvaxdata provides a collection of routines for converting numeric data — integer and floating-point — to and from the formats used on a Digital Equipment Corporation¹ (DEC) VAX 32-bit minicomputer (Brunner, 1991). Since the VAX numeric data formats are inherited from those used on a DEC PDP-11 16-bit minicomputer, these routines can be used to convert PDP-11 data as well. VAX numeric data formats are also the default data formats used on DEC Alpha 64-bit minicomputers running OpenVMS (Hewlett-Packard, 2005a, 2005b).

The libvaxdata routines are callable from Fortran or C. They require the caller uses two's-complement format for integer data and IEEE 754 format (ANSI/IEEE, 1985) for floating-point data. They also require the “natural” size of a C `int` type (integer) is 32 bits. That is the case for most modern 32-bit and 64-bit computer systems. Nevertheless, you may wish to consult the Fortran or C compiler documentation on your system to be sure.

Some Fortran compilers support conversion of VAX numeric data on-the-fly when reading or writing unformatted files, either as a compiler option or a run-time I/O option (Hewlett-Packard, 2002, 2005b). This feature may be easier to use than the libvaxdata routines. Consult the Fortran compiler documentation on your system to determine if this alternative is available to you.

Description

The routines in libvaxdata are:

<code>from_vax_i2()</code>	16-bit integer byte swap
<code>from_vax_i4()</code>	32-bit integer byte reversal
<code>from_vax_r4()</code>	32-bit VAX <code>F_floating</code> to IEEE <code>S_floating</code>
<code>from_vax_d8()</code>	64-bit VAX <code>D_floating</code> to IEEE <code>T_floating</code>
<code>from_vax_g8()</code>	64-bit VAX <code>G_floating</code> to IEEE <code>T_floating</code>
<code>from_vax_h16()</code>	128-bit VAX <code>H_floating</code> to Alpha <code>X_floating</code>
<code>to_vax_i2()</code>	16-bit integer byte swap
<code>to_vax_i4()</code>	32-bit integer byte reversal
<code>to_vax_r4()</code>	32-bit IEEE <code>S_floating</code> to VAX <code>F_floating</code>
<code>to_vax_d8()</code>	64-bit IEEE <code>T_floating</code> to VAX <code>D_floating</code>
<code>to_vax_g8()</code>	64-bit IEEE <code>T_floating</code> to VAX <code>G_floating</code>
<code>to_vax_h16()</code>	128-bit Alpha <code>X_floating</code> to VAX <code>H_floating</code>

¹ Later Compaq Computer Corporation, now Hewlett-Packard Company.

where *x_floating* is the nomenclature used on a DEC Alpha for its floating-point formats (Sites and Witek, 1995). *S_floating* is the IEEE 754 32-bit Single Format. *T_floating* is the IEEE 754 64-bit Double Format. *X_floating* is an IEEE 754-conforming 128-bit Double Extended Format.²

All calls take 3 arguments, an input array, an output array, and a conversion count:

C

```

Declaration #include "convert_vax_data.h"
Prototype  void name( const void *in_array, void *out_array,
                    const int *count );
Usage      #define ARRAY_LEN n
           data_type in_array[ARRAY_LEN],
           out_array[ARRAY_LEN];
           const int count = ARRAY_LEN;
           name( in_array, out_array, &count );

```

Fortran

```

Declaration Subroutine NAME( in_array, out_array, count )
           Integer count
           data_type in_array(count), out_array(count)
Usage      Integer ARRAY_LEN
           Parameter ( ARRAY_LEN = n )
           data_type in_array(ARRAY_LEN),
           & out_array(ARRAY_LEN)
           Call NAME( in_array, out_array, ARRAY_LEN )

```

where *name* (*NAME*) is the name of a libvaxdata routine, *n* (*count*) is the number of array elements to be converted, and *data_type* is an appropriate data type for the input (*in_array*) and output (*out_array*) data arrays. The *in_array* and *out_array* parameters may refer to the same array, since conversion is carried out element-by-element from *in_array* to *out_array*. The *in_array* and *out_array* parameters must not otherwise overlap.

Integer Conversions

VAXes and Intel 80x86 systems (Intel, 2005) store integers in two's-complement format, ordering the bytes in memory from low-order (l) to high-order (h), called little-endian format:

<i>Byte no.</i>	3	2	1	0
<i>16-bit integer</i>			hhhhhhhh	llllllll
<i>32-bit integer</i>	hhhhhhhh	nnnnnnnn	mmmmmmmm	llllllll

² The Alpha *X_floating* format is not necessarily compatible with another system's IEEE 754-conforming 128-bit floating-point format. In particular, it is *not* compatible with the IEEE 754-conforming 128-bit extended floating-point format implemented in software for IBM XL Fortran for AIX (International Business Machines, 2004). It *is* compatible with the IEEE 754-conforming 128-bit extended floating-point format defined for the Hewlett-Packard PA-RISC (Kane, 1995).

Apple Macintosh systems (Apple Computer, 2005) and most Unix systems (e.g., Sun [Sun Microsystems, 2005a], IBM [Silha, 2005], HP) also store integers in two's-complement format, but use the opposite (big-endian) byte ordering:

<i>Byte no.</i>	0	1	2	3
<i>16-bit integer</i>	hhhhhhhhl11111111			
<i>32-bit integer</i>	hhhhhhhhnnnnnnnnnmmmmmmmmll11111111			

A VAX-format integer is converted to big-endian format by reversing the byte order. No conversion is required when the caller uses little-endian byte order; the data are copied as-is (unless `in_array` and `out_array` are the same array, in which case the copy is skipped altogether).

Floating-Point Conversions

Intel 80x86 systems (Intel, 2005), Apple Macintosh systems (Apple Computer, 2004), and most Unix systems (Hewlett-Packard, 2002) implement the IEEE 754 floating-point arithmetic standard. VAX and IEEE formats are similar, after the bytes are rearranged. (VAX floating-point formats inherit the PDP-11 memory layout based on 16-bit words in little-endian byte order.)

The high-order bit is a sign bit (*s*). This is followed by a biased exponent (*e*), and a (usually) hidden-bit normalized mantissa (*m*). They differ in the number used to bias the exponent, the location of the implicit binary point for the mantissa, and the representation of exceptional numbers (e.g., \pm infinity).

VAX floating-point formats: $(-1)^s \times 2^{(e-bias)} \times 0.1m$

<i>Bit no.</i>	31	23	15	7	0	
<i>F_floating</i>	mmmmmm_m1_mmmmmmmseeeeeemm_m0_m					bias=128
<i>D_floating</i>	mmmmmm_m1_mmmmmmmseeeeeemm_m0_m mmmmmm_m3_mmmmmmmmmmmmm_m2_mmmmmmm					bias=128
<i>G_floating</i>	mmmmmm_m1_mmmmmmmseeeeeeeee_m0_m mmmmmm_m3_mmmmmmmmmmmmm_m2_mmmmmmm					bias=1024
<i>H_floating</i>	mmmmmm_m0_mmmmmmmseeeeeeeeeeeee mmmmmm_m2_mmmmmmmmmmmmm_m1_mmmmmmm mmmmmm_m4_mmmmmmmmmmmmm_m3_mmmmmmm mmmmmm_m6_mmmmmmmmmmmmm_m5_mmmmmmm					bias=16384

IEEE floating-point formats: $(-1)^s \times 2^{(e-bias)} \times 1.m$ (normalized)
 $(-1)^s \times 2^{(1-bias)} \times 0.m$ (subnormal)

<i>Bit no.</i>	31	23	15	7	0	
<i>S_floating</i>	seeeeeeeemm_m0_mmmmmmmmm_m1_mmmmmmm					bias=127
<i>T_floating</i>	seeeeeeeee_m0_mmmmmmmmm_m1_mmmmmmm					bias=1023

```

mmmmmm_m2_mmmmmmmmmmmmmmmmmmmmm_m3_mmmmm
X_floating      seeeeeeeeeeeeeeeeeemmmmmmm_m0_mmmmm    bias=16383
mmmmmm_m1_mmmmmmmmmmmmmmmmmmmmm_m2_mmmmm
mmmmmm_m3_mmmmmmmmmmmmmmmmmmmmm_m4_mmmmm
mmmmmm_m5_mmmmmmmmmmmmmmmmmmmmm_m6_mmmmm

```

VAX format to IEEE format Conversions

After rearranging the bytes, a VAX floating-point number is converted to IEEE floating-point format by subtracting $(1 + VAX_bias - IEEE_bias)$ from the exponent field to (1) adjust from VAX $0.1m$ hidden-bit normalization to IEEE $1.m$ hidden-bit normalization and (2) adjust the bias from VAX format to IEEE format. True zero ($s=e=m=0$) and dirty zero ($s=e=0, m \neq 0$) are special cases which must be recognized and handled separately.

Numbers whose absolute value is too small to represent in the normalized IEEE format illustrated above are converted to subnormal format ($e=0, m \neq 0$). Numbers whose absolute value is too small to represent in subnormal format are set to zero (silent underflow).

Overflow during the conversion is not possible; the largest floating-point number in each VAX format is smaller than the largest floating-point number in the corresponding IEEE floating-point format.

If the mantissa of the VAX floating-point number is too large for the corresponding IEEE floating-point format, bits are simply discarded from the right. Thus, the remaining fractional part is chopped, not rounded to the lowest-order bit. This can only occur when the conversion requires IEEE subnormal format.

A VAX floating-point reserved operand ($s=1, e=0, m=any$) causes a SIGFPE exception to be raised. The converted result is set to zero.

IEEE format to VAX format Conversions

Conversely, an IEEE floating-point number is converted to VAX floating-point format by adding $(1 + VAX_bias - IEEE_bias)$ to the exponent field. +zero ($s=e=m=0$), -zero ($s=1, e=m=0$), \pm infinity ($s=any, e=all-1's, m=0$), and NaNs ($s=any, e=all-1's, m \neq 0$) are special cases which must be recognized and handled separately. Infinities and NaNs cause a SIGFPE exception to be raised. The result returned has the largest VAX exponent ($e=all-1's$) and zero mantissa ($m=0$) with the same sign as the original.

Numbers whose absolute value is too small to represent in the normalized VAX format illustrated above are set to zero (silent underflow). (VAX floating-point formats do not support subnormal numbers.) Numbers whose absolute value exceeds the largest representable VAX-format number cause a SIGFPE exception to be raised (overflow). (VAX floating-point formats do not have reserved bit patterns for infinities or NaNs.) The result returned has the largest VAX exponent and mantissa ($e=m=all-1's$) with the same sign as the original.

The bytes are then rearranged to the VAX 16-bit word floating-point format.

Examples

The following C function, `from_vax_rhdr()`, converts the floating-point data header from a data file written on a VAX:

```

/* VAX Data Conversion Routines */

#include "convert_vax_data.h"

```

```

#ifdef FORTRAN_LINKAGE
#define FORTRAN_LINKAGE
#endif

/***** from_vax_rhdr() */
void FORTRAN_LINKAGE from_vax_rhdr( const void *inbuf, void *outbuf ) {

    register const float *in;          /* Microsoft C: up to 2 register vars */
    register float *out;              /* Microsoft C: up to 2 register vars */
    int n;
    float in_null, out_null;

    in = (const float *) inbuf;
    out = (float *) outbuf;

    in_null = in[1];
    n = 1;
    from_vax_r4( &in_null, &out_null, &n );

    n = 38;                            /* 1..38  binary */
    from_vax_r4( in, out, &n );
    in += n;
    out += n;

    *out = ( *in == in_null ) ? out_null : *in ; /* 39  ASCII */
    in++;
    out++;

    n = 89;                            /* 40..128 binary */
    from_vax_r4( in, out, &n );
}

```

The equivalent Fortran subroutine, FROM_VAX_RHDR, is:

```

***** FROM_VAX_RHDR
*
*   Subroutine FROM_VAX_RHDR( inbuf, outbuf )
*
*   Real inbuf[128], outbuf[128]
*
*   Real in_null, out_null
*
*
*   in_null = inbuf[2]
*   Call FROM_VAX_R4( in_null, out_null, 1 )
*
*   Call FROM_VAX_R4( inbuf[ 1], outbuf[ 1], 38 )
*
*   If ( inbuf[39] .eq. in_null ) Then
*       outbuf[39] = out_null
*   Else
*       outbuf[39] = inbuf[39]
*   End If
*
*
*

```

1..38 binary
39 ASCII
40..128 binary

```

    Call FROM_VAX_R4( inbuf[40], outbuf[40], 89 )
*
    Return
    End

```

Compilation

The C source code for the libvaxdata routines is in `convert_vax_data.c` in the `src` directory of the distribution kit. The C function prototypes are declared in `convert_vax_data.h` in the same directory.

To compile all routines into a single object module:

```
$ cc -c convert_vax_data.c
```

To compile a single routine into its own module, define `MAKE_routine_name`, substituting the upper-case name of the routine for `routine_name`, and give the object module a name. This is useful, for example, to insert the routines into a library such that a linker may extract only the routines actually needed by a particular program. For example, to compile only `from_vax_r4()`:

```
$ cc -c -o from_vax_r4.o -DMAKE_FROM_VAX_R4 \
    convert_vax_data.c
```

Two variants of `convert_vax_data.c` are available using `IS_LITTLE_ENDIAN` and `APPEND_UNDERSCORE`.

If `IS_LITTLE_ENDIAN` is defined as 0 (false), then the conversions are performed for a big-endian system; byte reordering is done for all VAX data types. If `IS_LITTLE_ENDIAN` is defined as 1 (true), then byte reordering is done for floating-point formats only; integer formats are identical to their VAX counterparts.

If `IS_LITTLE_ENDIAN` is not defined, then it is defined as 1 (true) if any of the following macros is defined:

<code>vax __vax vms</code> <code>__vms __alpha</code>	DEC VAX C, GNU C on a DEC VAX or a DEC Alpha, or DEC C
<code>M_I86 __M_IX86</code> <code>__M_ALPHA</code>	Microsoft 80x86 C or Microsoft Visual C++ on an Intel 80x86 or a DEC Alpha
<code>i386 __i386</code>	Sun C, GNU C, or Intel C on an Intel 80x86
<code>__x86_64</code> <code>__x86_64__</code>	GNU C or Portland Group C on an AMD Opteron or an Intel EM64T

If `APPEND_UNDERSCORE` is defined, the entry point names are compiled with an underscore appended. This is required so that they can be called from Fortran in cases where the Fortran compiler appends an underscore to externally called routines (e.g., Sun Fortran [Sun Microsystems, 2005b]). For example, to create Fortran-callable versions of all the routines in an object module called `fconvert_vax_data.o` on a Sun SPARC system, the compiler command would be:


```
$ cc -c -o fconvert_vax_data.o -DIS_LITTLE_ENDIAN=0 \
-DAPPEND_UNDERSCORE convert_vax_data.c
```

because a SPARC is a big-endian system and Sun Fortran appends an underscore to externally called routines.

`convert_vax_data.c` assumes an ANSI C compiler. Compilation will fail if a `char` is not 8 bits, a `short` is not 16 bits, or an `int` is not 32 bits.³ `convert_vax_data.c` does not use 64-bit arithmetic.⁴

Distribution Kit

The `libvaxdata` distribution kit includes make files and batch command files to create a (static) library of separately compiled modules for both Fortran and C programs. A single library is created, called `libvaxdata.x`, where `x` is the system suffix for object module libraries (e.g., `libvaxdata.a` on Unix).

To create the library:

1. Download or copy from CD the compressed distribution kit in a format suitable for your system (they are all identical). For example, use `libvaxdata.zip` on a Windows system.
2. Unpack the distribution kit. The most recent versions of Windows, Mac OS X, and Linux have built-in support to unpack the distribution kit directly from the desktop. (E.g., double-click the distribution kit to unpack it or open it, then drag-and-drop the contents from there.) Otherwise, a GUI tool may be available such as WinZip on Windows, or Stuffit Expander on a Macintosh. From a Linux command line, use `tar -xzf libvaxdata.tgz`. On Unix systems without a tar that can decompress an archive, use `zcat libvaxdata.tgz | tar -xf -`. You should see top-level directories named for each supported system type (e.g., `linux`, `macosx`, `win32`, etc.) and one named `src`, containing the C source files.
3. Open a terminal window (Command Prompt on Windows, MPW Shell on Mac OS 9) and navigate to the directory appropriate for your system. For example, Windows users should `cd` to the `libvaxdata\win32` directory. Follow the instructions in the `readme.txt` file there. The command to create the library will be something like:

```
> vcmake           Windows (Visual C++)
$ @Make           OpenVMS (CC)
make.mrc         Mac OS 9 (MrC)
$ make -f makefile.gcc  Unix/Linux/Mac OS X (gcc)
```
4. You can then copy the library to a system-wide directory for everyone to use, such as `/usr/local/lib` on Unix or Linux. Or, you can copy it to your own library directory, such as `~/lib` on Unix or Linux. See the `readme.txt` file for the instructions to use the library from your Fortran and C programs.

³ On a system whose “natural” size of a C `int` type (integer) is 16 bits, it may be possible to `#define int long` and change the test `UINT_MAX != 4294967295U` to `ULONG_MAX != 4294967295UL` in `convert_vax_data.c`. However, this has not been tested.

⁴ It may be possible to compile a version of `libvaxdata` for SMP parallel execution, since each conversion is independent. However, this has not been tested. To enable conversions in parallel across the outer loop over the conversion count, it may be necessary to assert that `in_array` and `out_array` are not aliased (i.e., do not overlap).

The distribution kit includes another useful routine to determine at run-time whether the system uses little-endian byte ordering:

C

```
Prototype    int is_little_endian( void );  
Usage        if ( is_little_endian() ) ...
```

Fortran

```
Declaration Integer Function IS_LITTLE_ENDIAN()  
Usage        If ( IS_LITTLE_ENDIAN() .ne. 0 ) ...
```

The prototype is not defined in `convert_vax_data.h`, so it must be explicitly declared in a C program.

References Cited

- ANSI/IEEE Std 754-1985, IEEE Standard for Binary Floating-Point Arithmetic, Institute of Electrical and Electronics Engineers, New York, NY.
- Apple Computer, Inc., 2004, Inside Macintosh: PowerPC Numerics (http://developer.apple.com/documentation/Performance/Conceptual/Mac_OSX_Numerics/Mac_OSX_Numerics.pdf).
- Apple Computer, Inc., 2005, Mac OS X ABI Function Call Guide (<http://developer.apple.com/documentation/DeveloperTools/Conceptual/LowLevelABI/LowLevelABI.pdf>).
- Brunner, Richard A., Ed., 1991, VAX Architecture Reference Manual, Second Edition, Digital Press, Bedford, MA.
- Hewlett-Packard Company, 2002, Compaq Fortran User Manual for Tru64 UNIX and Linux Alpha Systems, Order no. AA-Q66TE-TE (<http://h21007.www2.hp.com/dspp/files/unprotected/Fortran/docs/unix-um/dfum.htm>).
- Hewlett-Packard Company, 2005a, HP C User's Guide for OpenVMS Systems, Order no. AA-PUNZM-TK (<http://h71000.www7.hp.com/commercial/c/docs/ug.pdf>).
- Hewlett-Packard Company, 2005b, HP Fortran for OpenVMS User Manual, Order no. AA-QJRWD-TE (<http://h71000.www7.hp.com/doc/82final/6443/aa-qjrwd-te.pdf>).
- Intel Corporation, 2005, IA-32 Intel Architecture Software Developer's Manual, Volume 1: Basic Architecture, Order no. 253665-017 (<http://download.intel.com/design/Pentium4/manuals/25366517.pdf>).
- International Business Machines, Corp., 2004, XL Fortran Enterprise Edition for AIX User's Guide, Version 9.1, Order no. SC09-7898-00 (<http://www-1.ibm.com/support/docview.wss?uid=swg27005408&aid=1>).
- Kane, Gerry, 1995, PA-RISC 2.0 Architecture, Prentice-Hall (http://h21007.www2.hp.com/dspp/tech/tech_TechDocumentDetailPage_IDX/1,1701,2533,00.html).
- Silha, Ed, and others, 2005, PowerPC User Instruction Set Architecture, Book I, Version 2.02, International Business Machines Corp. (<ftp://www6.software.ibm.com/software/developer/library/es-ppcbook1.zip>).
- Sites, Richard L., and Witek, Richard T., 1995, Alpha AXP Architecture Reference Manual, Second Edition, Digital Press (an imprint of Butterworth-Heinemann), Newton, MA.
- Sun Microsystems, Inc., 2005a, Sun Studio 10, C User's Guide, Order no. 819-0494-10 (<http://docs-pdf.sun.com/819-0494/819-0494.pdf>).

Sun Microsystems, Inc., 2005b, Sun Studio 10, Fortran Programming Guide, Order no. 819-0491-10 (<http://docs-pdf.sun.com/819-0491/819-0491.pdf>).